


Tallies

An Introduction



MCNP® and Monte Carlo N-Particle® are **registered trademarks owned by Los Alamos National Security, LLC, manager and operator of Los Alamos National Laboratory. Any third party use of such registered marks should be properly attributed to Los Alamos National Security, LLC, including the use of the ® designation as appropriate.**

- Please note that trademarks are adjectives and should not be pluralized or used as a noun or a verb in any context for any reason.
- Any questions regarding licensing, proper use, and/or proper attribution of Los Alamos National Security, LLC marks should be directed to trademarks@lanl.gov.



Fundamentals

MCNP6 Output



MCNP6 can generate a lot of output for the “outp” file.

- **Output that is always there**
- **Output that you can turn on or off via the print card**
- **User requested / defined tallies**

Automatic Output



MCNP6 automatically creates standard summary information that gives the user a better insight into the physics of the problem and the adequacy of the Monte Carlo simulation.

- a complete listing of the input
- a complete accounting of the creation and loss of all tracks and their energy
- the number of tracks entering and re-entering a cell plus the track population in the cell
- the number of collisions in a cell
- the average weight, mean free path, and energy of tracks in a cell
- the activity of each nuclide in a cell (that is, how particles interacted with each nuclide, not the radioactivity)
- a complete weight balance for each cell
- KCODE cycle summaries
- basic print tables

- **Much information is organized in print tables that can be turned on or off.**
 - Only limited information about fluxes, spectra, reaction rates, etc.
- **The tables are numbered.**
 - Table number appears in the upper right-hand corner of the table, providing a convenient pattern when scanning the output file with an editor.
 - The pattern is PRINT TABLE n , where n is always preceded by one space and is a two- or three-digit number.

The Print Card



PRINT **x**

x = no entry ... gives the full, basic output print

x = $x_1 x_2$ (positive entries) ... prints basic output plus the tables specified by the table numbers x_1, x_2, \dots

x = $-x_1 -x_2$ (negative entries) ... prints full, basic output except the tables specified by x_1, x_2, \dots

Default: No PRINT card in the INP file or no PRINT option on the execution line will result in a reduced output print.

“**basic**” tables can’t be turned off; “**default**” tables printed automatically can be turned off.

Use is **optional** but **highly recommended**.

Table of Print Tables (1)



Table Number	Type	Description
10		Source coefficients and distribution
20		Weight window information
30		Tally description
32		Mesh tally description
35		Coincident detectors
40		Material composition
50		Cell volumes and masses, surface areas
60	basic	Cell importances
62	basic	Forced collision and exponential transform
70		Surface coefficients
72	basic	Cell temperatures
80		ESPLT/TSPLT Importance Ratios
85		Electron range and straggling tables
86		Electron bremsstrahlung and secondary production
90		KCODE source data
98		Physical constants and compile options

Table of Print Tables (2)



Table Number	Type	Description
100	basic	Cross-section tables
102		Assignment of $S(\alpha, \beta)$ data to nuclides
110		First 50 starting histories
120		Analysis of the quality of your importance function
126		Particle activity in each cell
128		Universe map
130		Neutron/photon/electron weight balance
140		Neutron/photon nuclide activity
150		DXTRAN diagnostics
160		TFC bin tally analysis
161	default	$f(x)$ tally density plot (empirical history score PDF)
162	default	Cumulative $f(x)$ and tally density plot
170	shorten	Source distribution frequency tables, surface source
175		Estimated $keff$ results by cycle
178	basic	Estimated $keff$ results by batch size
190		Weight window generator summary
198		Weight windows from multi-group fluxes
200	basic	Weight window generated windows

What is a tally?

- Not explicitly defined in the MCNP manual
- Manual states that the code “provides” them

Some definitions:

- A record of a reckoning, score, or count
- A number or group of items recorded
- A tabulation of results

Getting Results from MCNP6



- **MCNP produces k-eff information in tables.**
- **In fixed-source problems, MCNP6 gives no physical results by default.**
 - Analogous to running an experiment without any detectors or measuring equipment!
- **Tallies are analogous to measurement devices in experiments.**
- **Tallies in MCNP6 are often called edits in many other codes**
 - Fluxes
 - Currents
 - Reaction rates
- **Edits in MCNP are associated with its unstructured mesh feature.**

Tally Types



■ MCNP6 tally types:


- F1: Current on a surface
- F2: Flux on a surface
- F4: Flux in a cell (track-length estimate)
- F5: Flux at a point or ring detector
- F6: Energy deposition (track-length estimate)
- F7: Fission energy deposition (track-length estimate)
- F8: Pulse height tally
- FMESH: Mesh tallies

Basic Tallies



F1:<pl> - Current across surface

$$J = \frac{1}{W} \sum_{\text{all flights crossing surface}} wgt$$



W = total source weight

F2:<pl> – Flux on a surface

$$\phi = \frac{1}{A \cdot W} \sum_{\text{all flights crossing surface}} \frac{wgt}{|\mu|}$$


A = surface area

W = total source weight

$\mu = \Omega \cdot [\text{surface normal}]$

The concept of weight will be discussed in the variance reduction section. For now, consider $wgt = 1.0$

Basic Tallies




F4:<pl> - Flux in a cell

$$\phi = \frac{1}{V \cdot W} \sum_{\text{all flights in cell}} \text{wgt} \cdot \text{dist}$$



V = cell volume

W = total source weight



F5:<pl> - Flux at a point

$$\phi = \frac{1}{W} \sum_{\text{all collisions}} \text{wgt} \cdot \frac{p(\mu)e^{-\Sigma_T R}}{2\pi R^2}$$



F6:<pl> – energy deposition tally

F7:<pl> – fission energy deposition tally


- Volume tallies like F4
- Units of MeV/g, unless
- *F6 or *F7 then units are jerks/g

Tally Normalization & Units



- All MCNP6 tallies are normalized to be the response for **1 source particle**
- If your actual source strength is **4000 particles/sec**, then
 - MCNP6 tally results should be multiplied by 4000
 - Units for tallies should be “per second”
 - Applies when the **rate** of source particle production is known
- If your actual source strength is **4000 particles**, then
 - MCNP6 tally results should be multiplied by 4000
 - Units for tallies should not be “per second”
 - Applies the **total** source particle production is known (e.g., a pulse)
- You can have MCNP6 do the multiplication:
 - Supply the source strength on a tally multiplier card (**FMn card**)OR
 - Supply the source strength on the **sdef card** (include **wgt =** , but not recommended when using weight windows)

Tally Quantities Scored



Type	Where	Units
F1: Surface Current All particles	surface	#
F2: Surface Flux All particles	surface	# / cm ²
F4: Track length estimate of cell flux All particles	Cell	# / cm ²
F5: Flux at a point or ring detector N or P	point or ring	# / cm ²
F6: Track length est. of energy deposition. All particles	cell	MeV / g
F7: Track length est. of fission energy dep. N	cell	MeV / g
F8: Pulse height tally All particles	cell	pulses

The + Modifier



- A preceding plus-sign can be applied to F6 for collision heating (+F6) and F8 for charge deposition (+F8)
 - +F6 Collision heating **MeV/g**
 - Always applies to all particles listed on the mode card
 - No particle designator
 - +F8:<pl> Charge deposition **charge**
- The +F8 tally is the negative particle weight for electrons and the positive weight for positrons.
 - Refer to the MCNP manual for more information on the F8 tally, how it can be modified, and how it can be used.

The * Modifier (1)



- Tally types 1, 2, 4, and 5 are normally weight tallies (particles in the above table); however, if the F card is flagged with an asterisk (for example, *F1:N), energy times weight will be tallied.
 - *F1:<pl> MeV
 - *F2:<pl> MeV/cm2
 - *F4:<pl> MeV/cm2
 - *F5: <pl> MeV/cm2
- The asterisk flagging also can be used on tally types 6 and 7 to change the units from MeV/g to jerks/g (1 jerk = 1 GJ = 1e9 J).

The * Modifier (2)



- The asterisk on a tally type 8 converts from a pulse-height tally to an energy deposition tally.
 - *F8:<pl> MeV
- No asterisk can be used in combination with the + on the +F6 or +F8 tallies.

- 
- Los Alamos**
NATIONAL LABORATORY
EST. 1943


Operated by Los Alamos National Security, LLC for the U.S. Department of Energy's NNSA

F5 Tally Card Contents (Flux at Point)



■ Form: **Fn:<pl> X Y Z R**

- **n** = tally number = **5** + 10j $0 \leq j \leq 999$
- **<pl>** = particle type = particle symbol: n or p (no charged particles)
- At every collision, makes a deterministic estimate of flux
- **X, Y, Z** are position of tally where flux is desired
- **R** is the radius of a “sphere of constant flux”
 - Required to keep tally variance finite
 - Recommended to be about one mean free path
 - Use 0.0 in a void (vacuum) region



Tally Examples



F1:p (1 2) (3 4 5) 6

Photon surface current, 3 bins

F14:n 10 30 50

F4 neutron cell flux, 3 bins

F994:n (10 30) 50

F4 neutron cell flux, 2 bins

F44:p 10 11 12 T

F4 photon cell flux, 4 bins

F105:p 3.2 4.1 5.7 0.0

F5 photon flux at point, in a void

F35:n 100. 17. 0.0 5.0

F5 neutron flux at point, in a material

***F8:p 10 25**

**F8 tally of photon energy deposited
in cells, MeV**

Tallies Require Volumes or Areas



- For tallies (except F1, F5, F8) to be valid, MCNP6 must know a volume or area to perform the division.
- Sometimes, MCNP6 will be unable to calculate the volume of cells or areas of surfaces. You must then provide them!
- Three methods of doing this:
 - 1) Specify **vol = ####** on the respective cell card.
 - 2) Specify a list of volumes or areas for every cell or surface in the problem using the **VOL** or **AREA** cards:

VOL	V₁	V₂	.	.	.	V_m
AREA	A₁	A₂	.	.	.	A_n
 - 3) Use a **segment divisor (SD)** card.
 - 4) Volumes can be calculated via the stochastic volume calculation
 - requires special run
 - see manual

Segment Divisor Card (SD)



- **MCNP6 normalizes flux tallies by dividing by area, volume, or mass**
 - For cell flux tallies (F4), must divide by **volume**
 - For surface flux tallies (F2), must divide by **area**
 - For energy deposition (F6), must divide by **mass**
 - For fission heating (F7), must divide by **mass**
 - Can use SD card to supply areas, volumes, or masses
 - **MUST** do this if they are not calculated by MCNP6

- **Form: SDn d1 d2 ...**
 - n = tally number
 - d1, d2, ... = divisors for each tally bin
 - Must have as many entries as there are tally bins for tally "n"
 - Can use 1.0 to avoid dividing by volume or area or mass
 - Can be used to get total absorption, rather than absorption/vol
 - **Note: dividing by 1.0 instead of volume changes units, etc.**

Commenting Tallies in the Output File



- **Commenting on what tallies are calculated is important, especially if others may look at your output file!**

- Your co-workers will thank you!

- **Use of the FC card is recommended:**

FCn A String that is a Comment

- **Example**

F114:n 10

FC114 Cell flux tally in cell 10.

Tallies With Macrobodyes



- Surfaces of most macrobodies are formed by several distinct components (referred to as “facets”)
- Specific facet(s) must be specified for surface tallies
- Facet is identified as S.F, where S is the surface number for the macrobody and F is the facet number
- Facet numbers are fixed with respect to the orientation of the macrobody
- Examples

Rectangular Parallelepiped (RPP)

- 1 right side
- 2 left side
- 3 front
- 4 back
- 5 top
- 6 bottom


Right Circular Cylinder (RCC)

- 1 side of cylinder
- 2 top of cylinder
- 3 bottom of cylinder

Example



Surface and facet indices
for **shield01.txt**:



Input file for shield01.txt



shield01 - shielding calculation with 252-Cf neutron source

c >>>> cell cards

100	3000	-0.0013	-10	-20		\$ air left of shield
200	1000	-7.874	-10	20	-30	\$ iron shield left layer
210	2000	-1.0	-10	30	-40	\$ water layer
220	1000	-7.874	-10	40	-50	\$ iron shield right layer
300	3000	-0.0013	-10	50		\$ air right of shield
999	0		10			\$ rest of the world

c >>>> surface cards

10	rpp	-10	140	-100	100	-100	100	\$ problem bounding surfaces
20	px	0						\$ beginning of shield
30	px	10						\$ start of water layer
40	px	20						\$ end of water layer
50	px	40						\$ end of shield

c >>>> data cards

nps 1e5

c --- material specification

m1000	26056	1.0				\$ shield, pure iron-56
m2000	1001	2	8016	1		\$ water
mt2000	lwtr					\$ water s(a,b)
m3000	7014	0.8	8016	0.2		\$ air

c --- source specification

sdef pos=-5 0 0 erg=d1

sp1 -3 1.025 2.926 \$ 252-Cf spontaneous fission

c --- importances

imp:n 1 4r 0

Motivation



- Copy **shield01.txt** out of the SOLUTIONS directory.
- Analyze the input file and plot the geometry.
 - The shield is considered to be the iron – water – iron sandwich
- Run the problem

```
mcnp6    n = shield01.txt
```

- Note the following screen output:

```
warning.  there are no tallies in this problem.
```

- Analogous to running an experiment with no detection equipment!
- Examine the outp file

Example: shield02



- Copy **shield01.txt** to **shield02.txt**
- Insert tallies for:
 - Surface current at
 - Front (surface) of the shield facing source,
 - Back (surface) of the shield, and
 - Rightward surface of the rpp, 1 meter away from shield
 - Cell flux averaged over the entire shield
- Run the problem, analyze the output file
 - Search for the string **ltally**

Example: shield02



shield02 - shielding calculation with 252-Cf neutron source

c >>>> data cards

. . .

c --- tally specification

fc1 surface current entering, exiting, and 1 m after shield

f1:n 20 50 10.1

c

fc4 average neutron flux in the shield

f4:n (200 210 220)

Example: shield02 results



1tally 1 nps = 100000

surface current entering, exiting, and 1 m after shield
tally type 1 number of particles crossing a surface.
tally for neutrons

surface 20

7.88217E-01 0.0036

surface 50

5.36646E-03 0.0430

surface 10.1

2.56677E-03 0.0613

Example: shield02 results



```
1tally          4          nps =          1000
                    average neutron flux in the shield

tally type 4      track length estimate of particle flux
tally for neutrons

cell a is (200 210 220)

volumes

cell:            a

                    1.60000E+06

cell (200 210 220)

                    1.20763E-05  0.0055
```



Statistics and TFC discussion, pdf's & cdf's

Tally Fluctuation Chart



1tally fluctuation charts

nps	mean	tally error	vov	4 slope	fom
8000	1.2490E-06	0.1028	0.0421	0.0	3110
16000	1.2880E-06	0.0695	0.0178	10.0	3226
24000	1.2224E-06	0.0564	0.0119	7.4	3228
32000	1.2361E-06	0.0489	0.0088	7.4	3139
40000	1.2529E-06	0.0438	0.0066	10.0	3137
48000	1.2125E-06	0.0402	0.0057	10.0	3123
56000	1.2178E-06	0.0368	0.0048	10.0	3289
64000	1.2124E-06	0.0345	0.0042	10.0	3252
72000	1.1955E-06	0.0325	0.0037	10.0	3263
80000	1.2238E-06	0.0309	0.0033	10.0	3226
88000	1.2256E-06	0.0293	0.0030	10.0	3240
96000	1.2312E-06	0.0280	0.0028	10.0	3269
100000	1.2323E-06	0.0274	0.0026	10.0	3283

Assessing Results



- MCNP6 uses the Monte Carlo method.
 - Relies on repeated random sampling (of many cumulative distributions).
 - Results have statistical errors or uncertainties.
 - Always quote the errors when quoting the results.
- The influence of **statistical errors or noise** must be considered when assessing the reliability of Monte Carlo results.
- MCNP6 provides uncertainties and performs **statistical checks** to attempt to assess whether or not the results are reliable.
 - Results of tests **don't** prove reliability!!!
 - The tests look for things that seem wrong.
 - The tests **don't** prove that results are correct.
- Confidence intervals assume that the **Central Limit Theorem** is satisfied.
 - The arithmetic mean of a sufficiently large number of samples of identically distributed, independent random variables, each with a finite mean and variance, will approach a normal distribution, regardless of the underlying distribution.

Review: Basic Statistics



- MCNP6 tally results have the form

RESULT RELERR

Where

RESULT = average score for the tally, after N histories

RELERR = relative error in the average score, after N histories

All tally results are normalized to be per starting particle

- Exception: For KCODE calculations, K-effective results are reported as

RESULT STD

Where

RESULT = average K_{eff} score for the tally, after N histories

STD = standard deviation in the average score, after N histories

■ Average, standard deviation, relative error

- Let $x_k =$ the value of a tally for the k^{th} history
 $N =$ number of histories run (so far)

- Average tally**, after N histories
$$\bar{X} = \frac{1}{N} \sum_{k=1}^N x_k$$
- Sample standard deviation** of a tally average, after N histories

$$S_{\bar{X}} = \sqrt{\frac{1}{N-1} \sum_{k=1}^N (x_k - \bar{X})^2} \approx \sqrt{\frac{1}{N} \sum_{k=1}^N x_k^2 - \bar{X}^2}$$

- Relative error** in average tally, after N histories

$$RELERR = R = \frac{S_{\bar{X}}}{\bar{X}} \quad RELERR \propto S_{\bar{X}} \propto \frac{1}{\sqrt{N}}$$

Review: Basic Statistics



■ Relative error vs number of histories (N)

$$RELERR \propto S_{\bar{x}} \propto \frac{1}{\sqrt{N}}$$

- To cut the relative error in **half**, must run **four times** as many histories
- To reduce relative error by **10x**, must run **100x times** as many histories

■ Precision

The RELERR or STD DEV reflect the **precision** of results, i.e., the uncertainty in the result caused by statistical fluctuations in the Monte Carlo simulation.


■ Accuracy

The **accuracy** of a result is how close the average tally is to the true physical quantity being estimated.

Accuracy depends on the geometry approximations, cross-section data realism, material definitions, physics approximations, code approximations, etc.

- **Running more histories will improve the precision of a result, not the accuracy of a result.**

Interpreting R



For n identical scores and $n \ll N$ (n out of N) $R = 1/\sqrt{n}$

Range of R	Tally Quality
0.5 – 1.0	Garbage
0.2 – 0.5	Factor of a few
0.1 – 0.2	Questionable
< 0.10	Generally reliable <u>except</u> for point detectors
< 0.05	Generally reliable for point detectors

■ Confidence interval

- Using the computed STD DEV as an estimate of σ , we can estimate, by the Central Limit Theorem, the probability that the true mean lies with an interval:

$$\text{Prob} \left\{ \bar{x} - 1 \cdot s_{\bar{x}} \leq \mu \leq \bar{x} + 1 \cdot s_{\bar{x}} \right\} = 68\%$$

$$\text{Prob} \left\{ \bar{x} - 2 \cdot s_{\bar{x}} \leq \mu \leq \bar{x} + 2 \cdot s_{\bar{x}} \right\} = 95\%$$

$$\text{Prob} \left\{ \bar{x} - 2.6 \cdot s_{\bar{x}} \leq \mu \leq \bar{x} + 2.6 \cdot s_{\bar{x}} \right\} = 99\%$$

where μ is the true mean and σ is the true standard deviation.

- Think about what this means
 - If you repeat a calculation many times, it is likely that 1/3 of the time the true result will lie outside of the computed 1σ confidence interval.

Relative variance of the variance (VOV) – estimated relative variance of the estimated R.

- **Involves the estimated 3rd and 4th moments of the empirical history score PDF $f(x)$.**
- **Much more sensitive to large history score fluctuation than is R.**
- **Magnitude and behavior as a function of N are indicators of tally convergence and how well S approximates σ .**

$$\text{FOM} \equiv \frac{1}{R^2 T}$$

**Measure of
efficiency**

$$R^2 \propto 1/N$$

$$T \propto N$$

$R^2 T \sim \text{constant}$ within any one Monte Carlo run.

If tally is well behaved, the FOM \sim constant with the exception of very early in the problem.

Empirical History Score PDF, $f(x)$

What is it?

A histogram log-log plot of $f(x)$ vs x where

$$f(x_i) = \frac{NH_i}{N \cdot BW_i}$$

x = history score to the tally (score from 1 complete history)

N = total number of histories

NH_i = # of history scores in the i 'th score bin

BW_i = bin width for i 'th score bin

$$= x^{i+1} - x^i = 1.2589 x^i - x^i$$

The quantity 1.2589 is $10^{0.1}$ and comes from 10 equally spaced log bins per decade.

Instructor can show
where this appears
in the outp file

Pareto Fit of the largest x_i 's

$$\text{Pareto } f(x) = a^{-1} (1 + kx/a)^{-(1/k)-1}$$

- From this fit, the slope n in $1/x^n$ of the largest history scores x can be estimated to determine if and when the largest history scores decrease faster than $1/x^3$.
- Fits a number of extreme value distributions including:
 - $1/x^n$
 - Exponential ($k = 0$)
 - Constant ($k = -1$)

From the Pareto fit, the slope of $f(x_{large})$ is defined as

$$\text{SLOPE} \equiv (1/k) + 1$$

Where k is from the Pareto fit.

- 0 - not enough $f(x_{large})$ tail information exists for a slope estimate
- 10 - perfect score; max value; indicates an essentially negative exponential decrease
- >3 - satisfies the 2nd moment existence requirement for CLT
- >5 - 4th moment exists; VOV is believable

Extrapolating a large score tail that decreases less steeply than $1/x^3$ to infinity would produce an infinite 2nd moment, violating the CLT.


MCNP - Ten Statistical Checks



MCNP performs 10 statistical checks on tallies to try & assess whether the results are valid.

1. Estimated **mean** should have random behavior for last half of problem
2. Estimated **relative error** should be < 0.05 for point detector; < 0.10 for others
3. Estimated **RELERR** should monotonically decrease in last half of problem
4. Estimated **RELERR** should decrease as $1/N^{1/2}$ in last half of problem
5. Estimated **variance of the variance** (VOV) should be < 0.10
6. Estimated **VOV** should monotonically decrease in last half of problem
7. Estimated **VOV** should decrease as $1/N$ in last half of problem
8. Estimated **FOM** should not have obvious trends in last half of problem
9. Estimated **FOM** should show random behavior in last half of problem
10. Tail of underlying **tally probability density** should fall off as $1/x^m$, with $m > 3$

10 Statistical Checks Output



```
=====
```

results of 10 statistical checks for the estimated answer for the tally fluctuation chart (tfc) bin of tally										4
tfc bin	--mean--	-----relative error-----			----variance of the variance----			--figure of merit--		-pdf-
behavior	behavior	value	decrease	decrease rate	value	decrease	decrease rate	value	behavior	slope
desired	random	<0.10	yes	1/sqrt(nps)	<0.10	yes	1/nps	constant	random	>3.00
observed	random	0.03	yes	yes	0.00	yes	yes	constant	random	10.00
passed?	yes	yes	yes	yes	yes	yes	yes	yes	yes	yes

```
=====
```

this tally meets the statistical criteria used to form confidence intervals: check the tally fluctuation chart to verify.
the results in other bins associated with this tally may not meet these statistical criteria.

1status of the statistical checks used to form confidence intervals for the mean for each tally bin

tally result of statistical checks for the tfc bin (the first check not passed is listed) and error magnitude check for all bins

```
4 passed the 10 statistical checks for the tally fluctuation chart bin result
passed all bin error check: 1 tally bins all have relative errors less than 0.10 with no zero bins
```

the 10 statistical checks are only for the tally fluctuation chart bin and do not apply to other tally bins.

The FM Card

Reaction Rates



- Often some reaction rate, based on the flux or fluence, may be desired.

$$R_x = N\sigma_x\phi \quad \left(\frac{\text{nuclides}}{\text{barn} \cdot \text{cm}}\right) \circ \left(\frac{\text{barns}}{\text{nuclide}}\right) \circ \left(\frac{1}{\text{cm}^2 \cdot \text{sec}}\right) = \frac{1}{\text{cm}^3 \cdot \text{sec}}$$

Units = Reactions per unit volume (per unit time)

- Need some way to multiply the flux tally scores by the number density and the microscopic cross section for reaction x.
- MCNP can do this with the tally multiplier, or FM, card.
- Tally multiplier card can also scale by constants and has additional uses.

Reaction Rate Tallies



■ Fn card specifies:

- Type of tally - last digit of n
- Type of particle (e.g., F4:n)
- Location - cells or surfaces

■ FMn card specifies:

- Multiplier – constant, N, and/or N' s from a material
- Type of cross-section – many options

$$R_x = N \sigma_x \phi$$

Diagram illustrating the components of the reaction rate equation $R_x = N \sigma_x \phi$:

- N is associated with the **FMn card** (indicated by a red arrow).
- ϕ is associated with the **Fn card** (indicated by a red arrow).

Tally Multiplier Card



- **Note:** Discussion here will be limited to the multiplier form of the tally multiplication card.
- **Form:** $FMn \quad C \quad m \quad B_1 \quad (B_2 \dots B_i) \dots (B_j \dots B_m) \quad B_{last}$
 - **n** is tally number (e.g., FM24)
 - **C** is a multiplicative constant
 - $C > 0$ means -- multiply tally by C (e.g., source intensity constant)
 - $C < 0$ means -- multiply tally by $|C|$, and by **atom density** in the tally cell
 - **m** is a material number (from an Mm card)
 - Which atom density to use
 - **B_k** is a reaction type identifier
 - **B_{last}** is either blank or T (T sums over previous multiplier sets)

Combinations of Reaction Type Identifiers



- Reaction identifiers can be combined, either additively or multiplicatively, to form a single tally.
- All component identifiers must be enclosed in a single set of **parentheses**.
- **Colon** between two reaction type identifiers means they are to be **added** ($B_i : B_j : B_k$).
- **Blank** space between two reaction type identifiers means they are to be **multiplied** ($B_i B_j$).
- If no (), precedence of operations is **multiply** first, then **add**.

Reaction Type Identifiers



■ Reaction type identifiers can be either positive or negative

- Positive values correspond to ENDF reaction types (MT numbers)
- Negative values are MCNP-specific to the type of library (multi-group or continuous-energy) and particle (neutron or photon) employed

MT	Reaction Type
1	Total
2	Elastic scatter
18	Fission
101	Capture
102	(n,γ)
etc.	see Manual

Type	Neutrons		Photons
	Continuous	Multigroup	
-1	total*	total	incoherent scatt
-2	capture	fission	coherent scatt
-3	elastic scattering*	v (neutrons/fission)	photoelectric
-4	heating (MeV/coll)	χ (fission spectrum)	pair production
-5	γ production	capture	total
-6	fission	stopping power	photon heating
-7	v (neutrons/fission)	momentum transfer	
-8	Q (MeV/fission)		

Note: The definitions of capture and absorption differ depending upon whether you are a physicist or a nuclear engineer. Throughout this presentation, we will use

absorption = fission + capture

FM Card Examples



- Fission rate in cell 10, which contains material 100, with continuous-energy neutron data

F14:n 10

FM14 -1.0 100 -6

- Nu-fission rate in cell 10, which contains material 100, with continuous-energy neutron data

F24:n 10

FM24 -1.0 100 -6 -7

\$ number densities from mat 100

\$ ($\sigma_F \cdot v$)

- Absorption rate in cell 10, which contains material 100, with continuous-energy neutron data

F34:n 10

FM34 -1.0 100 -2 : -6

\$ number densities from mat 100

\$ ($\sigma_C + \sigma_F$)

Exercise: shield03 -- Gamma Production



- Copy **shield01.txt** to **shield03.txt**.
- Add tally to compute the total photon production rate in the iron portion of the shield.
 - Source strength of 3.0×10^8 neutrons per second
 - Note the units of the tally
(want total photon production rate in entire volume,
not production rate density)
- Run the problem and examine the output file.

Exercise: shield03 -- Gamma Production



shield03 - shielding calculation with 252-Cf neutron source

```
c >>>> data cards
```

```
. . .
```

```
c --- tally specification
```

```
fc4      photon production rate in iron
```

```
f4:n     (200  220)
```

```
fm4      -3.e8  1000  -5    $ source strength *  $\gamma$  product xs
```

```
sd4      1                $ do not divide by volume
```

Exercise: Gamma Production



```
1tally          4      nps = 100
                        photon production rate in iron
tally type 4      track length estimate of particle flux.
tally for neutrons

volumes

cell:      (200 220)

1.00000E+00

cell (200 220)

multiplier bin:  -3.00000E+08      1000      -5

1.63932E+08  0.0063
```

DE / DF Cards

Dose Rates

Calculating Dose in MCNP



- **There are two methods to compute dose (energy deposited per unit mass) in MCNP6:**
 - Explicit modeling of exposed targets (e.g., detectors, phantoms, etc.) and use of energy deposition (F6) tallies.
 - Flux tallies (F2, F4, or F5) with appropriate flux-to-dose conversion factors.
- **F6 tallies produce absorbed dose**
 - Units of rad or gray.
- **F2 or F4 tallies with “flux-to-dose” conversion factors produce biological dose**
 - Need “dose functions” to provide quality or tissue weighting factors.
 - Units of rem or sievert

Using the F6 Tally



- **If possible, model the target explicitly in the geometry and use an F6 tally to compute dose.**
 - Advantage: most exact as effects of target on radiation field is captured
 - Disadvantage: not always practical to model everything (e.g., locations of individuals standing in a room)
- **F6 tally is an F4 tally modified by the total cross section and heating number.**
 - Equivalent to an F4 tally and a FM4 card with (-1 -4).
 - Units are MeV/g; use FM card to convert units to rad or Gy.
- **Required to use DE and DF cards (next slide) with quality factors if biological dose required.**

Dose/Response Function Cards (DE, DF)



- Function to modify a tally response with some interpolated function (e.g. particle flux to human biological dose equivalent rate)

$$\text{Dose} = \int_E D(E)\phi(E)dE$$

DEn A E₁ E₂ . . . E_k

- E_i = energy points (MeV)
- A = LOG or LIN energy interpolation method

DFn B F₁ F₂ . . . F_k

- F_i = corresponding value of the dose function at each energy on DEn
- B = LOG or LIN dose interpolation method

- Appropriate for dosimetry when effect of “target” on the radiation field is small (e.g., a small detector)

Exercise: shield04 – Dose Calculation



- Copy **shield01.txt** to **shield05.txt**.
- Add tally to compute the biological dose rate (rem/hr) from neutrons to a worker standing 1 meter from the back of the shield
 - Source strength of 3.0×10^8 neutrons per second
 - Copy the DE and DF cards from the file: **shield_dedf.txt**
- Run the problem and examine the output file.

Exercise: shield05 – Dose Calculation



shield05 - shielding calculation with 252-Cf neutron source

```
c >>>> data cards
```

```
. . .
```

```
c ### tally specification
```

```
fc2      average dose rate in rem/hr, 1 m from shield from 3e8 neutrons
```

```
f2:n      10.1
```

```
fm2      3.e8      $ multiply by source strength 3.e8 n/s
```

```
c --- neutron flux to dose (rem/hr) factors
```

```
c !!! NOT RECOMMENDED FOR "OFFICIAL" CALCULATIONS !!!
```

de2	log	2.50e-8	1.00e-7	1.00e-6	1.00e-5	1.00e-4	1.00e-3
		1.00e-2	1.00e-1	5.00e-1	1.00e+0	2.50e+0	5.00e+0
		7.00e+0	1.00e+1	1.40e+1	2.00e+1		
df2	log	3.67e-6	3.67e-6	4.46e-6	4.54e-6	4.18e-6	3.76e-6
		3.56e-6	2.17e-5	9.26e-5	1.32e-4	1.25e-4	1.56e-4
		1.47e-4	1.47e-4	2.08e-4	2.27e-4		

Exercise: Dose Calculation



1tally 2 nps = 100000

average dose rate rem/hr, 1 m from shield from 3e8 neutrons

tally type 2 particle flux averaged over a surface.

tally for neutrons

this tally is modified by a dose function.

this tally is all multiplied by 3.00000E+08

areas

surface: 10.1

4.00000E+04

surface 10.1


1.63755E-03 0.0740

FMESH Tallies

Mesh Tallies



- **Mesh tallies cover 3D regions of space independent of the problem geometry**
 - Can be used to tally flux, reaction rates, heating, particle birth, fission source points, ...
 - Rectangular & cylindrical meshes
 - Bin on energy & time values
 - Number & size of mesh limited only by computer parameters
 - Can be rotated and translate
 - Modified by DE/DF or FM cards
 - Can't use built in DF functions
 - Plot results in MCNP
 - Each FMESH causes MCNP to re-track on the mesh – slower performance



FMesh Tally Card (1)



FMESHn : p **GEOM=** **ORIGIN=**
 IMESH= **IINTS=**
 JMESH= **JINTS=**
 KMESH= **KINTS=**
 AXS= **VEC=**
 EMESH= **EINTS=**
 FACTOR=

- Can be used with DEn, DF_n, and FM_n cards.
- **Caution:** It is easy to create huge mesh tallies that can fill computer memory.
- Each mesh invokes a particle re-tracking on that mesh.
- Other options are available – see the manual.

FMesh Tally Card (2)



GEOM	= mesh geometry: Cartesian (xyz or rec) or cylindrical (rzt or cyl)	xyz
ORIGIN	= x,y,z coordinates in MCNP cell geometry superimposed mesh origin	0. 0. 0.
IMESH	= coarse mesh locations in x (rectangular) or r (cylindrical) direction	---
IINTS	= number of fine meshes within corresponding coarse meshes	1
JMESH	= coarse mesh locations in y (rectangular) or z (cylindrical) direction	---
JINTS	= number of fine meshes within corresponding coarse meshes	1
KMESH	= coarse mesh locations in z (rectangular) or theta (cylindrical) direction	---
KINTS	= number of fine meshes within corresponding coarse meshes	1
EMESH	= values of coarse meshes in energy	all energies
EINTS	= number of fine meshes within corresponding coarse energy meshes	1
FACTOR	= multiplicative factor for each mesh	1.
AXS	= direction vector of the cylindrical mesh axis	0, 0, 1
VEC	= direction vector along with AXS that defines the plane for $\theta = 0$	1, 0, 0
TYPE	= plots primary sdf source particle starting locations in tally plotter	source

Example



- **Example:** 5 x 10 x 20 fission rate mesh tally in 5x5x5 cm box centered about the origin.

```
fmesh4:n      geom=xyz      origin=-2.5 -2.5 -2.5
              imesh=2.5      iints=5
              jmesh=2.5      jint=10
              kmesh=2.5      kints=20

fm4      -1.0      0      -6
```

- **Material index of zero is a wildcard, uses material in the current cell.**

Example of the FM card for FMESH





Calculate the average fission energy deposition

FM card format: FMn C m R1 R2

Put '0' as the material number

~~FM124 0.06925613 1 -6 -8~~

FM134 -1.0 0 -6 -8



Exercise: Mesh Tallies



- Copy **shield01.txt** to **shield04.txt**
- Insert a mesh tally to compute the energy deposition (in MeV/cm³) for a source of 3e8 neutrons/sec as a function of space.
 - Mesh should cover the entire shield (do not include air)
 - Use 40 elements in X, 40 in Y, and 1 in Z
 - Revisit the table of special reaction numbers for the FM card
 - Remember the “0” wildcard
- Run the problem and wait for instructions on plotting

Exercise: Mesh Tallies



shield04 - shielding calculation with Cf-252 neutron source

```
c >>>>> data cards
```

```
. . .
```

```
c --- mesh tally specification
```

```
fmesh4:n      geom=xyz      origin=0      -100      -100
```

```
              imesh=40      iints=40
```

```
              jmesh=100     jint=40
```

```
              kmesh=100     kints=1
```

```
fm4      -3.e8      0      -1      -4      $ ( sigtot * heating )
```

Mesh Tally Plotting



- In the command line type:

```
mcnp6      z      r = runtpe
```

- Where runtpe is the name of your **runtpe** file for shield04.
- The following commands in **red** are useful:

```
mcplot> fmesh 4           Brings up the results in the geometry plotter  
mcplot> fmrelerr          Plots the relative uncertainties
```

fmrelerr is only recognized in the geometry plotter.

Mesh Tally Plotting




```
02/12/16 15:13:44  
shield04 - shielding calculation  
with 252-Cf neutron source
```

```
probid = 02/12/16 15:02:42  
basis: XY  
( 1.000000, 0.000000, 0.000000)  
( 0.000000, 1.000000, 0.000000)  
origin:  
( 20.00, 0.00, 0.00)  
extent = ( 100.00, 100.00)
```

```
Mesh Tally      4  
nps             1000000  
runtpe = shield04.txtr  
dump            2
```

X-Y Slice



Mesh Tally Plotting




02/12/16 15:17:54
shield04 - shielding calculation
with 252-Cf neutron source

probid = 02/12/16 15:02:42
basis: XZ
(1.000000, 0.000000, 0.000000)
(0.000000, 0.000000, 1.000000)
origin:
(20.00, 0.00, 0.00)
extent = (100.00, 100.00)

Mesh Tally 4
nps 1000000
runtpe = shield04.txtr
dump 2

X-Z Slice



Mesh Tally Plotting




02/12/16 15:15:00
shield04 - shielding calculation
with 252-Cf neutron source

probid = 02/12/16 15:02:42
basis: XY
(1.000000, 0.000000, 0.000000)
(0.000000, 1.000000, 0.000000)
origin:
(20.00, 0.00, 0.00)
extent = (100.00, 100.00)

Mesh Tally 4
nps 1000000
runtpe = shield04.txtr
dump 2

Relative Error



UNCLASSIFIED

Spectra and Plotting

Obtaining Energy Spectra



- Often, spectral information is useful for a lot of problems, including shield design.
- An energy binning can be added to tallies with an E card:

En e1 e2 . . . ei . . . eK

- The index **n** corresponds to a tally index defined on the **F** card
 - If **n = 0**, then it is the default for all tallies
 - Each **ei** are energy bin boundaries in MeV
 - Implied lower bound is always 0 MeV
 - Tallies are integrated over the entire energy bin (not in per MeV)
- Also can bin in time with T card, or, for F1 tallies, in direction cosine with the C card.

Tally Plotting



- Copy **shield06.txt** out of SOLUTIONS directory, examine, run
- Read in the runtpe file to plot energy spectrum (tally 1) of current leaving shield

```
mcnp6  z    r = runtpe
```



- Replace “runtpe” with the name of your runtpe file

- In the plotting command window, type text in **red**:

tal 1	specifies the tally to plot
loglog	has plot on log-log scale
nonorm	removes per MeV normalization
xlim 1.e-8 1.e+1	sets the x-range of the plot window

- Should see an interesting feature around 20 keV

Tally Plotting



Cross Section Plotting



- Explain this behavior by plotting the cross section

- On the command line, type:

```
mcnp6  ixz  i = shield06.txt
```

- In the plotter, type the text in **red**:

```
xs      26056.80c
```

Brings up Iron-56 total xs

```
xlim    0.01  1
```

Sets energy view from 10 keV to 1MeV

```
ylim    1.e-3  1.e+3
```


Sets range of cross section

- Look at the graph of the total cross section in the resonance range
 - Notice the wide anti-resonance (cross section window) at about 20-30 keV

Cross Section Plotting



The infamous
“iron window”



TMESH Tallies (optional)

Track Averaged Mesh Tally (Type 1)

FORM: (R,C,S)MESHn:<p/> keyword = value

n = 1, 11, 21, 31,...

(note, number must not duplicate one used for an 'F1' tally)

<p/> is a particle type. There is no default.

Example:

```
tmesh
```

```
  rmesh1:n      flux
  cora1  -15.0 100i 15.0
  corb1  -15.0 15.0
  corc1  -30.5 100i 30.5
```

```
endmd
```

Mesh Tally Keywords (Type 1)



Keyword

Description

TRAKS

Tally the number of tracks through each mesh volume. No values accompany the keyword.

FLUX

Tally the average fluence (particle weight times track length divided by volume) in units of number/cm².

If the source is considered to be steady state in particles per second, then the value becomes flux in number/cm²-s.

TRANS

Translate and/or rotate the mesh, according to the specified TR card. Must be followed by a single TR card number.

Additional keywords:

DOSE, POPUL, PEDEP, MFACT

Source Mesh Tallies (Type 2)



Source Mesh Tally:

Form: (R,C,S)MESHn <pl₁> <pl₂>...<pl_n> trans = #

n = 2, 12, 22, 32, ...

(note, number must not duplicate one used for an 'F2' tally)

<pl> = particle type(s) (Up to 10 allowed)

trans = TRn card number used to translate and/or rotate the mesh

Energy Deposition Mesh Tallies (Type 3)



Energy Deposition Mesh Tally:

General Form: (R,C,S)MESHn *keyword*

$n = 3, 13, 23, 33, \dots$

Allowed keywords: see next slide

Example: Mesh tally of total energy deposited, all sources

tmesh

RMesh3 total

cora3 -15.0 100i 15.0

corb3 -15.0 15.0

corc3 -30.5 100i 30.5

endmd

Energy Deposition TMESH Keywords



Keyword Description

TOTAL	score energy deposited from any source
DE/DF	score ionization from charged particles
RECOL	Score energy transferred to recoil nuclei above table limits

Additional keywords

TLEST, DELCT, MFACT, NTERG, TRANS (see the manual)

DXTRAN Mesh Tally (Type 4)



General Form: (R,C,S)MESHn:<pl> trans = #

n = 4, 14, 24, 34, ...

(note, number must not duplicate one used for an 'F4' tally)

<pl> is a particle type. There is no default.

trans must be followed by a single reference to a TR card that can be used to translate and/or rotate the entire mesh.
Only one TR card is permitted with a mesh card.

TMESH Tally Plotting




From the command prompt:

```
mcnp6 z run = runtpe
```

```
mcplot> plot $brings up the geometry plotter
```

```
[buttons] tal, N, color
```



TMESH Tally Plotting



FORM: CONTOUR [cmin cmax cstep] [commands]

All command entries are optional.

cmin minimum contour value

cmax maximum contour value

cstep number of contour steps

% or pct interpret step values as percentages

log step values logarithmic with **cstep** interpolates

All contours normalized to min and max values of entire tally

noall contours normalized to min and max values of contour slice
(FIXED command)

line/noline do/don't draw lines around contours

color make color contour plot

nocolor contour lines only

TMESH Plot Contour Command Examples



EXAMPLES

CONTOUR 5 95 10 & line color

There will be 10 contour lines at 5%, 15%,...95% of the maximum value.

Lines will be drawn around the colored contours as in the figure.

Note: this is the default setting

CONTOUR 1e-4 1e-2 12 log

There will be 12 contour lines logarithmically spaced between 1e-4 and 1e-2


Tallies & Sources in Repeated Structures (optional)

Tallies in Repeated Structures




- **What's special about a tally or source in a repeated structure?**

- Must provide the path to tally or source cell
- Which pin cell ??



- **Enables tallies or sources in specific cells of repeated structures.**


Purpose and Definitions



■ Example - levels

c cell cards

1	0	-11	u=1		
2	0	11	u=1		
3	0	-22	fill=1		u=2
4	0	-33	fill=1	trcl(1 0 0)	u=2
5	0	22 33			u=2
6	0	-44	fill=2		



- Cell 6 is in the "real world", not a universe - called "Level 0"
Cells 3,4,5 are in Universe 2, which fills Cell 6 - called "Level 1"
Cells 1,2 are in Universe 1, which fills Cell 3 and Cell 4 - called "Level 2"
- The left pin (Cell 1) is contained in Cell 3, that is contained in Cell 6.
- Use the symbol "<" to mean "is contained in":

1	<	3	<	6	<-- This uniquely identifies the left pin
1	<	4	<	6	<-- This uniquely identifies the right pin

Geometric Paths & Tally Paths



■ Geometric chain


- A list of cells, one in each level of geometry, that uniquely specifies a particular cell in a repeated structure
- Start at the deepest level of geometry, finish in the real world

■ Tally path

- A subset of a geometric chain

■ Example

C1 < C2 == "Cell C1 is contained in Cell C2"



- All geometric paths: 1<3<6 2<3<6 1<4<6 2<4<6
 3<6 4<6 5<6 6

- Possible tally paths:

1<3<6	<-- the left pin
1<4<6	<-- the right pin
1<6	<-- BOTH pins

Tally Paths



FORM: $F_n:p$ ($E_1 < C_1 < C_2$) ...

- Left arrow (<) identifies levels within a tally chain, translate it to: **"is contained in"**
- Requires an outer set of parentheses.
- First level entries (E_i) are either:
 - **Tally surfaces** if tally type 1 or 2.
 - **Tally cells** if tally type 4, 6, 7, or 8
- Upper level entries (C_i) must be:
 - **Cells with a FILL entry that is nonzero.**
 - **Produces a tally only when a particle is in a geometric chain that corresponds to an input tally chain.**

Tally Paths



c cell cards

1 0 -11 u=1

2 0 11 u=1

c

3 0 -22 fill=1 u=2

4 0 -33 fill=1 trcl(1 0 0) u=2

5 0 22 33 u=2


6 0 -44 fill=2

C surface cards

. . .

C data cards -- flux tallies

F4:n (1<3<6) <-- the left pin
(1<4<6) <-- the right pin
(1<6) <-- BOTH pins



Tally Paths - Lattices



Form: $F_n:p \ ((E2 \ E3) < (\ C3 \ C4 \ [I1 \ \dots \ I2]) < (C5 \ C6)) \dots$

■ **Brackets, [], identify one or more elements of a lattice:**

- Must follow a filled lattice cell (C4).
- A lattice cell listed without brackets gives the union

■ **Three possible formats: over all lattice elements.**

$[I]$

Indicating the I-th lattice element in fully specified FILL array.

$[I1:I2 \ J1:J2 \ K1:K2]$

Indicating one or more lattice elements (see FILL card).

$[I1 \ J1 \ K1, \ I2 \ J2 \ K2, \ \dots]$

Indicating lattice element (I1, J1, K1), (I2, J2, K2), etc.

Tallies - Multiple Bin Format

- Automatically invoked for levels with multiple entries.
- Can be disabled at any level by () around all entries.
- Number of total bins generated is given by the product of the number of bins at each level.
- The order of generated tally bins can be important,
 - (E4 E5 < (C1 C2) < C3 C4) becomes:

(E4 < (C1 C2) < C3)	(E5 < (C1 C2) < C3)
(E4 < (C1 C2) < C4)	(E5 < (C1 C2) < C4)
 - A segment divisor entry (SD card) may be input for each generated tally bin.

Sources in Repeated Structures



- **KSRC Format**
- **SDEF CEL Format**

KSRC Format



- No special format for repeated structures
- Enter x,y,z locations in the coordinate system of the highest level (the real world)
- All source points are absolute coordinates, i.e., "real world" coordinates

Ksrc 1. 1. 1. 2. 3. 4. 5. 6. 7. . . .

From the manual:

- The coordinate system for position and direction sampling (pds) is the coordinate system of the first negative or zero C_i in the geometric path starting from the right and proceeding left.
- Each entry in the source path represents a geometry level, where level zero is the last source path entry, level one the second to the left, etc., and level zero is above level one, level two is below level one.
- The pds level is the level associated with the pds cell or pds coordinate system. All levels above the pds level must be included in the source path. Levels below the pds level need not be specified, and when given, may include one or more zero entries.
- The default pds level is the first entry in the source path when the path has no negative or zero entry.
- Position rejection is done in cells at all levels where $C_i \neq 0$, but if any C_i has a negative universe number on its cell card and is at or above the pds level, higher level cells are not checked.

SDEF CEL Format



- To use the SDEF card to select a particular cell inside a lattice,

SDEF x=d1 y=d2 z=d3 cel=d4

... (xyz position distributions) ...

SI4 L (geometric-path-to-cell)

SP4 1

- Example - center cell in Problem **tal08**

SDEF x=d1 y=d2 z=d3 cel=d4

SI1 -.7 .7

SP1 0 1

SI2 -.7 .7

SP2 0 1

SI3 -180. 180.

SP3 0 1

SI4 L (-10 < 40[0 0 0] < 50)

SP4 1

<-- xyz coordinates in "Level 2"

■ Example - all fuel pins in Problem fv5

```
SDEF    x=d1 y=d2 z=d3 cel=d4
SI1     -.7 .7
SP1     0 1
SI2     -.7 .7
SP2     0 1
SI3     -180. 180.
SP3     0 1
SI4 L   ( -10 < 40[-7:7 -7:7 0:0]< 50 )    $ xyz coordinates in "Level 2"
SP4     1 224r
```

Notes:

- (1) 15 x 15 x 1 = 225 lattice elements listed on SI4
- (2) Must give (relative) probability for each on SP4
- (3) The minus sign in SI4 indicates which coordinate system the x,y,z sampling is done in (Level 2)
- (3) Despite the order on the SDEF card,
the CEL parameter is chosen first, then x, then y, then z